


## Origin computer does not have internet access


### Computer information you must have before obtaining your license

If your computer does not have internet access, you can obtain a license using another computer that has internet access. To do this, you will need the Origin Computer ID, Authorization Code and Origin serial number from the computer without internet access.

1. In the Origin license dialog, select the option "Get a license file now. This computer does NOT have internet access." and click OK.




2. The dialog that opens displays your Origin serial number, computer name, Computer ID and Authorization Code. Click Dump to Notepad to save these as a text file or make note of these to obtain the license.



### Log in or join the OriginLab website

1. Go to a computer with internet access and open a web browser to [www.originlab.com](http://www.originlab.com).
2. Click the License/Register link in the bottom left corner of the page.



3. Log in if you have an account or create an account as needed.

### If this is the first time you are registering or licensing Origin with your log in account

1. In the page that opens after you log in, select the option "I want to register my Origin software and obtain a license file for a computer" and click Next.

- I want to register my Origin software and obtain a license file for a computer  
 I want to register my Origin software

Next

2. Select/enter your serial number and version and click Continue.
3. If you have a multi-seat node locked package, you will be asked to enter your Access Code. If you do not know your Access Code, contact your Origin administrator.

Enter Access Code:



If you do not know your Access Code, please contact your Origin administrator.

4. Next enter the Origin Computer ID, computer name and Authorization Code and click Submit.

Computer Name:

Computer ID:

Authorization Code:

Submit

(Press once only please!)

5. If you have a 1-seat node locked package, you will be asked to choose between an office or home license.

### License file generation


I am obtaining a license for:

- My office computer.  
 My home computer (limited to active maintenance period).


Next

The home use license will expire when your maintenance expires.

6. Your license will be generated and displayed on the web page. Copy all the license text displayed in the text box.



7. Open a text editor such as Notepad and Paste the license into Notepad. Save this text file to a flash drive or disk.
8. Now go back to your Origin computer. You need to return to the main license dialog, so if you still see the license dialog showing your computer details, click the Back button.
9. In the main license dialog, select "I have my license file or text already. What do I do next?" and click OK.



10. Copy and paste the license text into the Enter License dialog and click OK.